

PI Firmware Commands/Queries

**demo software commands
May 5, 2020**

TABLE OF CONTENTS

1.0 PI FIRMWARE 3

- 1.1 Source Repository, Compiling, and Executable 3
- 1.2 Metrics Captured 3
- 1.3 Capture Rate(s) 4

2.0 SOFTWARE SPECIFICATION 4

- 2.1 Timestamp, Date-Time Naming Convention 4
- 2.2 BlackBox Naming Convention 4
- 2.3 Log File5
 - 2.3.1 Log File Location:.....5
 - 2.3.2 Log File Structure.....5
 - 2.3.3 Log File Path.....6
 - 2.3.4 Log File Upload.....7

3.0 SOCKET INTERFACE SPECIFICATION 8

- 3.1 Socket Instantiation 8
- 3.2 Socket Command Structure 8
- 3.3 Query List 8
- 3.4 Command List 11
- 3.5 Client Connection 15

4.0 BLACKBOX SOFTWARE & SYSTEMD 16

1.0 PI FIRMWARE

1.1 Source Repository, Compiling, and Executable

The source code has all been written in C, for speed of execution and compatibility with the GPIO library used on the pi (bcm2835). The github repo where the source code can be accessed is:

https://github.com/johnpolakow/PI_Blackbox

The directory for code executing on the pi is "**PI_Firmware**". To get a sample client application, which already works with the pi firmware, look in the "**Client_Code**" folder.

For compiling the firmware on the pi, here is the command (make sure bcm2835 library has been installed if this is a fresh OS):

```
gcc -g -o exec Execution_Engine.c -l pthread -l bcm2835 -l m
```

If debugging capabilities are desired use this command:

```
gcc -g -fsanitize=address -static-libasan -o exec Execution_Engine.c -l pthread -l bcm2835 -l m
```

The client code is easy to compile:

```
gcc -o client client.c
```

IF EXECUTING MANUALLY, MUST EXECUTE PROGRAM WITH SUDO

Note: the binary executable for the program must be executed on the raspberry pi with the "sudo" command. The pi requires programs which access the GPIO pins to have elevated access. If sudo is not used there will be a segmentation fault.

```
sudo ./exec
```

Note2: By default the pi has been configured to automatically start execution of the program at boot, MANUAL EXECUTION IS NOT NECESSARY. Under normal circumstances it is not necessary to execute the program manually. If you desire to for testing or debug purposes, make sure to preface the command with sudo.

1.2 Metrics Captured

The metrics directly measured by the Pi Blackbox are:

- Power delivered to the Cooler Driver Board (Volts, mA, Watts)
- Dewar Temp Diode Voltage, and associated LUT temperature (Volts, Kelvins)
- Power delivered to heat load resistor in the Dewar (V, mA, mW)
- Heat Load State (On/Off)
- Relay State for Cooler Driver (On/Off)
- Temperature of x3 attached K-type thermocouples (Celsius)

1.3 Capture Rate(s)

Each metric once per second. Every second a complete iteration of the various metrics are read and saved to storage. The pi can be queried over the socket interface as often as necessary to retrieve the metrics. If querying more than once per second, examine the timestamp in the metrics readout to ascertain whether a duplicate read has been sent. The pi responds with whatever the latest data is.

The Pi firmware captures each metric sequentially, then writes the data points to file. Each datalog point of the above metrics is paired with:

- Timestamp (MM/DD/YYYY hh:mm:ss)
- Elapsed Running Time when sample taken

2.0 SOFTWARE SPECIFICATION

2.1 Timestamp, Date-Time Naming Convention

A timestamp shall be represented in the format:
[MM-dd-YYYY]_[hh.mm.ss]

MM	2 digit month
dd	2 digit day of month
YYYY	4 digit year
hh	2 digit hour
mm	2 digit minute
ss	2 digit second

* 2 digit refers to the convention of including a leading zero if the value is less than ten.

** To avoid AM/PM confusion, the two digit hour shall be in the 24 hour based format. For example the hour 6:01:35 PM is represented as 18:01:35

Example:

Timestamp for Jan. 27th 2020 @ 3:18:34 PM is- **01/27/2020_15.18.34**

2.2 Log File

2.2.1 Log File Structure

// filename: XXXXXX

PI_BB LOG FILE

firmware version XXXXX, PCB version

PI_BB: [blackbox#]

CCC: CCC_ID

Compressor: Compressor_ID

PI_Blackbox Software Behavioral Document

Dewar: Dewar_ID
Displacer: Displacer_ID
Test Execution: [Manual] or [profile filename]
Test_Type: [default/Performance/Lifetime/BurnIn]
Log Start: [Timestamp]

[COLUMN LEGEND]

DATA	[TIMESTAMP]
COMMAND	[TIMESTAMP]
DATA	[TIMESTAMP]
STOP	[TIMESTAMP]

To avoid confusion and misinterpretation, the units of measure are included in both the Legend and immediately following the value of each metric. For instance a voltage is recorded as:

12.013V

2.2.2 Log File Path

If a USB drive is inserted, the Linux kernel has been configured to mount it to:

/home/pi/USB_drive/

The flash drive is the default storage device if present. The Log file path is then:

/home/pi/USB_drive/Logs/filename.log

If a USB flash drive is not detected, the micro SD card will be used to store the data, and the path will be:

/home/pi/Logs/filename.log

The log file is automatically created and stored when the ">start_test" command is issued.

Note: When configuring the software to auto-launch at boot, it broke the save to USB functionality, so all Logs are being stored on the pi at:

/home/pi/Logs/filename.log

USB save functionality will be restored in the next software release.

PI_Blackbox Software Behavioral Document

2.2.3 Log File Upload

Currently the log file upload to hub is **not implemented**. The logs can be accessed manually however.

3.0 SOCKET INTERFACE SPECIFICATION

3.1 Socket Instantiation

The socket hosted on the pi opens and listens on port **2020**, waiting for any client to connect. The client can connect to the pi over Ethernet or Wifi, it is interface agnostic. The Pi listens on port 2020 for any incoming connection. The pi waits for clients to connect to it, the pi does not initiate any connections. The socket is configured as TCP/IP protocol, with the following socket parameters:

```
.ai_family = AF_INET;  
.ai_socktype = SOCK_STREAM;  
.ai_flags = AI_PASSIVE;
```

A sample client program has been written and is included to illustrate how to use the interface. The pi will always send a response to any client instruction.

3.2 Socket Command Structure

All “commands” or instructions will originate from the hub computer. There are two types of instructions sent to a PI_BB:

- Get Instruction– will refer to as a ‘Query’
- Set Instruction – referred to as a ‘Command’

Query Instructions must begin with a ‘?’.

Command Instructions must begin with a ‘>’.

If an instruction is sent without the proper prefix of ‘?’ or ‘>’, or there is a typo in the instruction, the parser responds with an error message.

The commands/queries are not case sensitive, even though the commands are shown as all capital letters in this document.

3.3 Query List

Not all queries are implemented yet. The non functional queries are greyed out.

?status Return the following parameters:

- hostname
- eth0 IP address
- wlan0 address
- flash drive disk usage
- SD card disk usage
- DUT ID for:

PI_Blackbox Software Behavioral Document

compressor

DDCA

displacer

CCC

Pi CPU temperature

Test status (whether executing a test or not)

Execution set to manual or profile

Current time & date on PI

```
***CLIENT*** ( HUB )

##: ?status
      hostname:  PI-BB38
      eth0 IP:   interface not up
      wlan0 IP:  10.198.20.237
      system time: 12:04:37
      USB disk use: 31% of 960M
      CPU_temperature: 52.6
      Test is Running: false
      Execution Mode: Manual Control
      Profile Name: N/A
      -----
      Compressor ID: not set
      DDCA ID: not set
      Displacer ID: not set
      CCC ID: not set
```

?profiles list the profiles currently stored on SD card

```
-----

***CLIENT*** ( HUB )

##: ?profiles
./Firmware/Profiles
├─ lifetime_test.profile
├─ performance_test.profile
├─ burn_in.profile
├─ custom1.profile
./USB_Drive/Profiles
├─ custom1.profile
└─ custom2.profile

-----
```

?logs list the logs currently stored on SD card

?profile list the current selected profile, if any

?show [filename] print the contents of the file. Could be a profile, log, config file, etc.

PI_Blackbox Software Behavioral Document

?metrics Returns a snapshot of the current measurements.

```
***CLIENT*** ( HUB )
```

##: ?metrics	CCC V	CCC A	CCC W	Dewar °K	diodeV	RLoad V	RLoad mA	R_PWR mW	°C	THRMCP °C	°C	Time	Date	Elapsed Time	Relay State
	0.021V	0.0023A	0.000W	300.7°K	0.6297V	0.00V	0.0mA	0.0mW	25.24°C	23.96°C	24.91°C	12:04:55	05/05/2020	not started	OFF

?time Current date-time PI thinks it it right now

```
***CLIENT*** ( HUB )

##: ?time
    05/05/2020 12:14:34
```

? If no argument is supplied with the query instruction, the list of query instructions is printed

```
***CLIENT*** ( HUB )

##: ?

Query list w/ args:
  ?HELP
  ?LOGS
  ?METRICS
  ? (print this list)
  ?PROFILES
  ?PROFILE
  ?TIME
  ?SHOW [filename]
  ?STATUS

DEBUG: Parse_Success, QUERY "" is valid.
```

PI_Blackbox Software Behavioral Document

help Prints query instructions and command instructions with usage info. Note this command does not require a '?' or '>'.

```
***CLIENT*** ( HUB )

##: help
List of Commands & Queries, w/ usage:
COMMANDS:

    >LOAD_ON
    >LOAD_OFF
    > (print this list)
    >RELAY_ON
    >RELAY_OFF
    >SET_LOAD [integer in milliWatts]
    >START_TEST
    >STOP_TEST
    >SET_MANUAL_MODE
    >SET_PROFILE_MODE
    >SELFTEST
    >SET_TIME [MM/dd/YYYY_HH.mm.ss] (HH is 24 hour based)
    >SEND_LOG
    >SEND_ALL_LOGS
    >SET_COMPRESSOR_ID [string]
    >SET_DISPLACER_ID [string]
    >SET_DDCA_ID [string]
    >SET_CCC_ID [string]
    >USE_PROFILE [filename]

QUERIES:
    ?HELP
    ?LOGS
    ?METRICS
    ? (print this list)
    ?PROFILES
    ?PROFILE
    ?TIME
    ?SHOW [filename]
    ?STATUS
```

3.4 Command List

DEBUG [ON/OFF] Turn additional debug information on or off. This may help when writing software to interface with the pi. Note the ">" character is not used to prepend the command with.

```
-----
***CLIENT*** ( HUB )

##: debug on
    ✓ changed debug output to ON

    DEBUG: Success, rec'vd debug instruction: "debug on"
    DEBUG: Success, rec'vd "debug on", parsed to DEBUG command
-----
```

PI_Blackbox Software Behavioral Document

```
***CLIENT*** ( HUB )  
##: debug off  
    ✓ changed debug output to OFF
```

VERBOSE [ON/OFF] Turn verbose responses on or off. Verbose responses include the column headers for the metrics command. Note the ">" character is not used to prepend the command with.

```
-----  
***CLIENT*** ( HUB )  
##: verbose off  
    ✓ changed verbose output to OFF  
-----
```

>START_TEST Starts test execution, within the confines of selected test parameters. At present, because profile functionality is not complete yet, the >start_test command only causes the log file to begin recording.

>RELAY_ON Turn on the relay.

```
-----  
***CLIENT*** ( HUB )  
##: >relay_on  
    ---RELAY ON---
```

>RELAY_OFF Turn off the relay.

```
-----  
***CLIENT*** ( HUB )  
##: >stop_test  
    Test Execution stopped.  
    ---RELAY OFF---
```

PI_Blackbox Software Behavioral Document

>SET_LOAD [value] Set the load resistor power dissipation in **milliWatts**. The load is not turned on with this command, just set to the value of the supplied argument. When the LOAD_ON command is issued, then power will be applied at the load dissipation value supplied in this command.

```
-----  
***CLIENT*** ( HUB )  
##: >set_load 100  
    ✓ Set load value to 100.0 mW .  
-----
```

>LOAD_ON Set the load resistor current to the value prescribed by the SET_LOAD command. Default load current is 0 if the load has not been set yet.

```
-----  
***CLIENT*** ( HUB )  
##: >load_on  
    ---LOAD ON---  
-----
```

>LOAD_OFF Turn load resistor current off. This command is only valid if a test is currently executing AND test execution is set to manual.

```
-----  
***CLIENT*** ( HUB )  
##: >load_off  
    ---LOAD OFF---  
-----
```

PI_Blackbox Software Behavioral Document

>STOP_TEST Turn off cooler relay. Turn off load resistor current. Stop data-logging.

```
-----  
***CLIENT*** ( HUB )  
##: >stop_test  
    Test Execution stopped.  
  
    ---RELAY OFF---  
-----
```

>SET_MANUAL_MODE Set test execution to manual. Default value is manual mode.

>SET_PROFILE_MODE Set test execution to the current profile setting. This command works, however running a profile is not implemented yet.

>USE_PROFILE [profile] The file given as an argument is now selected as the profile to be executed. Verify the profile exists. The profile file is parsed to validate it is acceptable. Begin test execution by issuing START_TEST.

>SELFTEST Run the built-in self test operations and report back results. Not implemented yet.

>SET_TIME [MM-dd-YYYY]_[hh.mm.ss] Set Pi to argument timestamp.

>SEND_LOG upload log file(s) from the last test to the hub. This may span more than one file if the test lasted more than one day. Not implemented yet.

>SEND_ALL_LOGS upload all log files stored on the flash drive to the hub PC. If no flash drive is present, an error message is displayed regarding missing flash drive. Not implemented.

>SET_COMPRESSOR_ID

```
-----  
***CLIENT*** ( HUB )  
##: >set_compressor_id CMP1234  
    ✓ Compressor ID set to: CMP1234  
-----
```

>SET_DISPLACER_ID

>SET_DEWAR_ID

>SET_CCC_ID

PI_Blackbox Software Behavioral Document

- If no argument is supplied with the Command instruction, the list of all Commands is printed.

```
***CLIENT*** ( HUB )

##: >

Command list w/ args:
>LOAD_ON
>LOAD_OFF
> (print this list)
>RELAY_ON
>RELAY_OFF
>SET_LOAD [integer in milliWatts]
>START_TEST
>STOP_TEST
>SET_MANUAL_MODE
>SET_PROFILE_MODE
>SELFTEST
>SET_TIME [MM/dd/YYYY_HH.mm.ss] (HH is 24 hour based)
>SEND_LOG
>SEND_ALL_LOGS
>SET_COMPRESSOR_ID [string]
>SET_DISPLACER_ID [string]
>SET_DDCA_ID [string]
>SET_CCC_ID [string]
>USE_PROFILE [filename]
```

3.5 Client Connection

When a client connects, the following welcome message is sent by the pi:

```
Connecting to server 10.198.20.237 on PORT 2020
```

The image shows a large, stylized ASCII art representation of a cat's face. The face is composed of various symbols like slashes (/), backslashes (\), underscores (_), hyphens (-), and pipes (|) arranged to form the features of the cat, including its ears, eyes, whiskers, and nose. The entire graphic is rendered in yellow/gold color against a dark background.

4.0 BLACKBOX SOFTWARE & SYSTEMD

To configure the firmware to launch at boot, it was turned into a service launched by the **systemd** kernel subsystem. A file called "Blackberry.service" is located at:

/lib/systemd/system/Blackberry.service

Systemd auto-launches the executable at boot, and if the executable fails or quits for some reason, systemd will continuously attempt to relaunch the executable. This is good and verifies as long as the pi is on, we can connect to it.

One downside of the auto-launch feature is the executable doesn't launch in a terminal instance, so you can't monitor commands and events as they happen on the pi. If you want to monitor the output on the pi you can stop the service, and launch the standalone executable. Here's how to do it:

To stop the service:

sudo systemctl stop Blackberry.service

To restart the service:

sudo systemctl start Blackberry.service

To see the status:

sudo systemctl status Blackberry.service

To disable the service from auto-launching at boot:

sudo systemctl disable Blackberry.service

To enable the service from auto-launching at boot:

sudo systemctl enable Blackberry.service

If for some reason the service is not working, you can view the error reporting in the following locations:

dmesg

journalctl

/var/log/boot.log

/var/log/daemon.log

/var/log/messages

/var/log/syslog

/var/log/user.log